
ecx

Release 0.1.0dev0

Milan Skocic

Jan 07, 2026

CONTENTS

1	Getting Started	3
2	Examples	5
3	APIs	7
4	Programs	15
5	Changelog	19
	Python Module Index	21

Modern Fortran

A purple rounded rectangle containing the white text "ECX".

ECX

Electrochemistry for Fortran.

GETTING STARTED

1.1 Introduction

ecx a Fortran library for providing a collection of routines for electrochemistry. A C API allows usage from C, or can be used as a basis for other wrappers. A Python wrapper allows easy usage from Python.

To use *ecx* within your *fpm* project, add the following lines to your file:

```
[dependencies]
ecx = { git="https://github.com/MilanSkocic/ecx.git" }
```

1.2 Dependencies

```
gcc>=10
gfortran>=10
fpm>=0.7
stdlib>=0.7
```

1.3 Installation

A Makefile is provided, which uses *fpm*, for building the library.

- On windows, *msys2* needs to be installed. Add the *msys2* binary (usually C:\msys64\usr\bin) to the path in order to be able to use *make*.
- On Darwin, the *gcc* toolchain needs to be installed.

```
chmod +x configure.sh
./configure.sh
make
make test
make install
make uninstall
```

You need a compiler that can compile the *stdlib*.

1.4 License

MIT

EXAMPLES

2.1 Fortran

```
program example_in_f
  use iso_fortran_env
  use ecx
  implicit none

  real(real64) :: w(3) = [1.0d0, 1.0d0, 100.0d0]
  real(real64) :: r = 100.0d0
  real(real64) :: p(3) = 0.0d0
  character(len=1) :: e
  integer :: errstat
  complex(real64) :: zout(3)
  character(len=:), pointer :: errmsg

  p(1) = r
  e = "R"
  call z(p, w, zout, e, errstat, errmsg)
  print *, zout
  print *, errstat, errmsg

end program
```

2.2 C

```
#include <stdio.h>
#include <stdlib.h>
#include "ecx.h"

int main(void){

  int errstat, i;
  double w[3] = {1.0, 1.0, 1.0};
  double p[3] = {100.00, 0.0, 0.0};
  ecx_cdouble z[3] = {ecx_cbuild(0.0,0.0),
                      ecx_cbuild(0.0, 0.0),
```

(continues on next page)

(continued from previous page)

```

                                ecx_cbuild(0.0, 0.0));
char *errmsg;

ecx_eis_z(p, w, z, 'R', 3, 3, &errstat, &errmsg);

for(i=0; i<3;i++){
    printf("%f %f \n", creal(z[i]), cimag(z[i]));
}
printf("%d %s\n", errstat, errmsg);
return EXIT_SUCCESS;
}

```

2.3 Python

```

from pyecx import eis
import matplotlib.pyplot as plt

R = 100
C = 1e-6
w = np.logspace(6, -3, 100)

p = np.asarray([R, 0.0, 0.0])
zr = np.asarray(eis.z("R", w, p))
p = np.asarray([C, 0.0, 0.0])
zc = np.asarray(eis.z("C", w, p))
zrc = zr*zc / (zr+zc)
print("finish")

fig = plt.figure()
ax = fig.add_subplot(111)

ax.set_aspect("equal")
ax.plot(zrc.real, zrc.imag, "g.", label="R/C")

ax.invert_yaxis()

plt.show()

```

3.1 Fortran

<https://milanskocic.github.io/ecx/ford/index.html>

3.1.1 ecx (module)

Main module for ecx.

3.1.2 ecx__api (module)

API Procedures

get_version (function)

function get_version() -> fptr

Get the version.

Returns

fptr

[character(len=:), pointer] Version of the library.

kTe (function)

pure elemental function kTe(T) -> r

Compute the thermal voltage.

Arguments

T

[real(dp), intent(in)] Temperature in °C.

Returns

r

[real(dp)] Thermal voltage in V.

z (subroutine)

subroutine z(p, w, zout, e, errstat, errmsg)

Arguments

p

[real(dp), intent(in), dimension(:)]

w
[real(dp), intent(in), dimension(:)] Angular frequencies in rad.s-1

zout
[complex(dp), intent(out), dimension(:)] Complex impedance in Ohms.

e
[character(len=1), intent(in)] Electrochemical element: R, C, L, Q, O, T, G

errstat
[integer(int32), intent(out)] Error status

errmsg
[character(len=:), intent(out), pointer] Error message

mm (subroutine)

subroutine mm(p, w, zout, n)

Arguments

p
[real(dp), intent(in), dimension(:)] Compute the measurement model.

w
[real(dp), intent(in), dimension(:)] Parameters.

zout
[complex(dp), intent(out), dimension(:)] Angular frequencies in rad.s-1

n
[integer(int32), intent(in)] Complex impedance in Ohms.

nernst (function)

pure function nernst(E0, z, aox, vox, ared, vred, T) -> E

Compute the Nernst electrochemical potential in V.

Arguments

E0
[real(dp), intent(in)]

z
[integer(int32), intent(in)] Standard electrochemical potential in V.

aox
[real(dp), intent(in), dimension(:)] Number of exchanged electrons.

vox
[real(dp), intent(in), dimension(:)] Activities of the oxidants.

ared
[real(dp), intent(in), dimension(:)] Coefficients for the oxidants.

vred
[real(dp), intent(in), dimension(:)] Activities of the reductants

T
[real(dp), intent(in)] Coefficients for the reductants.

Returns

E
[real(dp)] Temperature in °C.

sbv (function)

pure elemental function sbv(U, OCV, j0, aa, ac, za, zc, A, T) -> I

Arguments

U
[real(dp), intent(in)] Open Circuit Voltage in V.

OCV
[real(dp), intent(in)] Compute Butler Volmer equation without mass transport.

j0
[real(dp), intent(in)] Electrochemical potential in V.

aa
[real(dp), intent(in)] Exchange current density in A.cm-2.

ac
[real(dp), intent(in)] Anodic transfer coefficient.

za
[real(dp), intent(in)] Cathodic transfer coefficient.

zc
[real(dp), intent(in)] Number of exchnaged electrons in the anodic branch.

A
[real(dp), intent(in)] Number of exchnaged electrons in the cathodic branch.

T
[real(dp), intent(in)] Area in cm2.

Returns

I
[real(dp)] Temperature in °C.

bv (function)

pure elemental function bv(U, OCV, j0, jdla, jdla, aa, ac, za, zc, A, T) -> I
Compute Butler Volmer equation with mass transport.

Arguments

U
[real(dp), intent(in)] Open Circuit Voltage in V.

OCV
[real(dp), intent(in)]

j0
[real(dp), intent(in)] Electrochemical potential in V.

jdla
[real(dp), intent(in)] Exchange current density in A.cm-2.

jdla
[real(dp), intent(in)] Anodic diffusion limiting current density in A.cm-2.

aa
[real(dp), intent(in)] Cathodic diffusion limiting current density in A.cm-2.

ac
[real(dp), intent(in)] Anodic transfer coefficient.

za
[real(dp), intent(in)] Cathodic transfer coefficient.

zc
[real(dp), intent(in)] Number of exchnaged electrons in the anodic branch.

A
[real(dp), intent(in)] Number of exchnaged electrons in the cathodic branch.

T
[real(dp), intent(in)] Area in cm2.

Returns

I
[real(dp)] Temperature in °C.

3.1.3 ecx__capi (module)

Procedures

capi_get_version (function)

```
function capi_get_version()bind(c, name="ecx_get_version") -> cptr
```

C API - Get the version.

Returns

cptr
[type(c_ptr)]

capi_nm2eV (subroutine)

```
pure subroutine capi_nm2eV(lambda, E, n)bind(C, name="ecx_core_nm2eV")
```

Arguments

lambda
[real(c_double), intent(in), dimension(n)] Wavelength in nm.

E
[real(c_double), intent(out), dimension(n)] Energy in eV.

n
[integer(c_size_t), intent(in), value] Size of lambda and E.

capi_kTe (subroutine)

```
pure subroutine capi_kTe(T, kTe_, n)bind(C, name="ecx_core_kTe")
```

Arguments

T
[real(c_double), intent(in), dimension(n)] Temperature in °C.

kTe_
[real(c_double), intent(out), dimension(n)] Thermal voltage in V.

n
[integer(c_size_t), intent(in), value] Size of T and kTe.

capi_z (subroutine)

subroutine capi_z(p, w, zout, e, k, n, errstat, errmsg)bind(C, name="ecx_eis_z")

Arguments

p
[real(c_double), intent(in), dimension(k)] Parameters.

w
[real(c_double), intent(in), dimension(n)] Angular frequencies in rad.s⁻¹

zout
[complex(c_double_complex), intent(out), dimension(n)] Complex impedance in Ohms.

e
[character(len=1,kind=c_char), intent(in), value] Electrochemical element: R, C, L, Q, O, T, G

k
[integer(c_size_t), intent(in), value] Size of p

n
[integer(c_size_t), intent(in), value] Size of w

errstat
[integer(c_int), intent(out)] Error status

errmsg
[type(c_ptr), intent(out)] errmsg Error message

capi_nernst (function)

pure function capi_nernst(E0, z, aox, vox, nox, ared, vred, nred, T)bind(C, name="ecx_kinetics_nernst") -> E

Compute the Nernst electrochemical potential in V.

Arguments

E0
[real(c_double), intent(in), value]

z
[integer(c_int), intent(in), value] Standard electrochemical potential in V.

aox
[real(c_double), intent(in), dimension(nox)] Number of reductants.

vox
[real(c_double), intent(in), dimension(nox)] Activities of the oxidants.

nox
[integer(c_size_t), intent(in), value] Number of exchanged electrons.

ared
[real(c_double), intent(in), dimension(nred)] Coefficients for the oxidants.

vred

[real(c_double), intent(in), dimension(nred)] Activities of the reductants

nred

[integer(c_size_t), intent(in), value] Number of oxidants.

T

[real(c_double), intent(in), value] Coefficients for the reductants.

Returns**E**

[real(c_double)] Temperature in °C.

capi_sbv (subroutine)

```
pure subroutine capi_sbv(U, OCV, j0, aa, ac, za, zc, A, T, I, n)bind(c,  
name="ecx_kinetics_sbv")
```

Compute Butler Volmer equation without mass transport.

Arguments**U**

[real(c_double), intent(in), dimension(n)] Open circuit potential in volts.

OCV

[real(c_double), intent(in), value] Size of U and I.

j0

[real(c_double), intent(in), value] Potential in volts.

aa

[real(c_double), intent(in), value] Exchange current density in A.cm-2.

ac

[real(c_double), intent(in), value] Anodic transfert coefficient.

za

[real(c_double), intent(in), value] Cathodic transfert coefficient.

zc

[real(c_double), intent(in), value] Number of exchanged electrons in anodic branch.

A

[real(c_double), intent(in), value] Number of exchanged electrons in cathodic branch.

T

[real(c_double), intent(in), value] Area in cm2.

I

[real(c_double), intent(out), dimension(n)] Temperature in °C.

n

[integer(c_size_t), intent(in), value]

capi_bv (subroutine)

```
pure subroutine capi_bv(U, OCV, j0, jdla, jdle, aa, ac, za, zc, A, T, I, n)bind(c,  
name="ecx_kinetics_bv")
```

Compute Butler Volmer equation without mass transport.

Arguments

U
[real(c_double), intent(in), dimension(n)] Open circuit potential in volts.

OCV
[real(c_double), intent(in), value] Size of U and I.

j0
[real(c_double), intent(in), value] Potential in volts.

jdl
[real(c_double), intent(in), value] Exchange current density in A.cm-2

jdlc
[real(c_double), intent(in), value] Anodic diffusion limiting current density in A.cm-2.

aa
[real(c_double), intent(in), value] Cathodic diffusion limiting current density in A.cm-2.

ac
[real(c_double), intent(in), value] Anodic transfert coefficient.

za
[real(c_double), intent(in), value] Cathodic transfert coefficient.

zc
[real(c_double), intent(in), value] Number of exchanged electrons in anodic branch.

A
[real(c_double), intent(in), value] Number of exchanged electrons in cathodic branch.

T
[real(c_double), intent(in), value] Area in cm2.

I
[real(c_double), intent(out), dimension(n)] Temperature in °C.

n
[integer(c_size_t), intent(in), value]

3.2 C

```
#ifndef ECX_H
#define ECX_H
#include <complex.h>
#if _MSC_VER
    #define ADD_IMPORT __declspec(dllimport)
    typedef _Dcomplex ecx_cdouble;
    #define ecx_cbuild(real, imag) (_Cbuild(real, imag))
#else
    #define ADD_IMPORT
    typedef double _Complex ecx_cdouble;
    #define ecx_cbuild(real, imag) (real+I*imag)
#endif

extern char* ecx_get_version(void);

ADD_IMPORT extern const double ecx_core_PI;
```

(continues on next page)

(continued from previous page)

```
ADD_IMPORT extern const double ecx_core_T_K;
void ecx_core_nm2eV(double *lambda, double *E, size_t n);
void ecx_core_kTe(double *U, double *kTE, size_t n);

extern double ecx_kinetics_nernst(double E0, int z,
                                   double *aox, double *vox, size_t nox,
                                   double *ared, double *vred, size_t nred,
                                   double T);

extern void ecx_kinetics_sbv(double *U, double OCV, double j0,
                             double aa, double ac, double za, double zc,
                             double A, double T, double *i, size_t n);

extern void ecx_kinetics_bv(double *U, double OCV, double j0, double jdla, double jdle,
                             double aa, double ac, double za, double zc,
                             double A, double T, double *i, size_t n);

extern void ecx_eis_z(double *p, double *w, ecx_cdouble *z,
                     char e, size_t k, size_t n,
                     int *errstat, char *(*errmsg));

#endif
```

3.3 Python

Python wrapper of the (Modern Fortran) ecx library.

PROGRAMS

4.1 ecxcli (program)

```

program ecxcli
  !! CLI interface for electrochemistry.
  use ieee_arithmetic, only: ieee_is_nan
  use iso_fortran_env, only: real64, int32, output_unit
  use ecx
  use ciaaw, only: ciaaw_version => get_version, get_saw, print_periodic_table,&
    get_z_by_symbol

  use M_CLI2
  implicit none

  integer :: i
  integer(int32) :: zmass
  real(real64) :: r, dr
  character(len=32) :: cmd
  character(len=:), allocatable, target :: help_text(:), version_text(:), usage_text(:)
  character(len=:), pointer :: char_fp(:)
  character(len=3) :: elmt

  nullify(char_fp)

  help_text=[character(len=80) :: &
    'NAME', &
    '  ecxcli(1) - Command line for ecx', &
    ', &
    'SYNOPSIS', &
    '  ecxcli SUBCOMMAND [OPTIONS ...] ARGS ...', &
    ', &
    'DESCRIPTION', &
    '  ecxcli is command line interface for computing electro-', &
    '  chemical properties:', &
    '    o EIS      Electrochemical Impedance Z=f(w)', &
    '    o Kinetics  j=f(U)', &
    '    o PEC      Iph=f(hv, U)', &
    ', &
    '  It can also provide the molar masses, isotope compositions and', &
    '  nuclide compositions.', &
    ', &
    'SUBCOMMANDS', &
    ', &
  ]

```

(continues on next page)

(continued from previous page)

```

' o all  Get the whole periodic table.           ', &
' o saw  Get the standard atomic weight.          ', &
!' o ice  Get the isotopic composition of the element. ', &
!' o naw  Get the nuclide atomic weight.          ', &
'                                     ', &
' Enter ecxcli SUBCOMMAND --help for detailed descriptions. ', &
'                                     ', &
'OPTIONS                                     ', &
' o --abridged, -a      Use the abridged value.    ', &
' o --uncertainty, -u   Use the uncertainty.        ', &
' o --pprint           Nice formatting.            ', &
' o --mass, -z         Get the mass number.        ', &
'                                     ', &
'VALID FOR ALL SUBCOMMANDS                 ', &
' o --help             Show help text and exit    ', &
' o --verbose          Display additional information when available. ', &
' o --version          Show version information and exit. ', &
'                                     ', &
'' ]

version_text=[character(len=80) :: &
'PROGRAM:      ecxcli           ', &
'DESRIPTION:   Command line for ecx ', &
'VERSION:      '//get_version()//' ', &
'AUTHOR:       M. Skocic        ', &
'LICENSE:      MIT              ', &
'' ]

usage_text=[character(len=80) :: &
'Usage: ecxcli SUBCOMMAND [OPTIONS...][--help|--version] ELEMENTS...', &
'' ]

cmd = get_subcommand()
call set_mode('strict')

select case (cmd)
case ("saw")
call set_args("--abridged:a --uncertainty:u --mass:z --pprint", get_help_
↪ saw(), version_text)
if(size(unnamed) == 1) then
write(output_unit, "(A)") "Enter at least one element."
char_fp => usage_text
call print_text(char_fp)
stop
end if
do i=2, size(unnamed)
elmt = unnamed(i)
zmass = get_z_by_symbol(elmt)
if(lget("pprint"))then
r = get_saw(elmt,abridged=lget("a"))
dr = get_saw(elmt, abridged=lget("a"), uncertainty=.true.)
if(lget("mass"))then

```

(continues on next page)

(continued from previous page)

```

write(output_unit, '(A4, A3, A3, SP, G14.6, A3, ES14.2, S, A5,
↪I3, A1)') &
    'SAW_', elmt, " = ", r, "+/-", dr, ' (Z=', zmass, ') '
else
    write(output_unit, '(A4, A3, A3, SP, G14.6, A3, ES14.2)') &
        'SAW_', elmt, " = ", r, "+/-", dr
end if
else
    r = get_saw(elmt,abridged=lget("a"), uncertainty=lget("u"))
    if(lget("mass"))then
        write(output_unit, '(I4, 4X, G0.16)') zmass, r
    else
        write(output_unit, '(G0.16)') r
    end if
end if
end do
case ("all")
    call set_args(" ", help_text, version_text)
    call print_periodic_table()
case default
    call set_args(" ", help_text, version_text)
    char_fp => usage_text
    call print_text(char_fp)
end select

```

contains

```

function get_help_saw()result(res)
    !! Get the help text for the subcommand saw.
    character(len=80), allocatable :: res(:)
    res = [character(len=80) :: &
        'NAME', &
        ' saw - th ecxcli subcommand to get the standard atomic weight.', &
        ' ', &
        'SYNOPSIS', &
        ' ecxcli saw [OPTIONS ...] ELEMENTS ...', &
        ' ', &
        'DESCRIPTION', &
        ' Provide the saw either abridged or not.', &
        ' The uncertainty of the saw can be retrieved too.', &
        ' ', &
        'OPTIONS', &
        ' o --abridged, -a Use the abridged value.', &
        ' o --uncertainty, -u Use the uncertainty.', &
        ' o --pprint Nice formatting.', &
        ' o --mass, -z Get the mass number.', &
        ' ', &
        'VALID FOR ALL SUBCOMMANDS', &
        ' o --help Show help text and exit', &
        ' o --verbose Display additional information when available.', &
        ' o --version Show version information and exit.', &
        ' ', &
    ]

```

(continues on next page)

(continued from previous page)

```
'EXAMPLE
' Minimal example
'   ecxcli saw H
'   ecxcli saw -a -u 0
'   ecxcli saw H C B O Zr Nb --pprint
'   ecxcli saw -a H C B O Zr Nb --pprint
'
'' ]
end function

subroutine print_text(char_fp)
  character(len=:), pointer, intent(in) :: char_fp(:)
  integer :: i
  do i=1, size(char_fp), 1
    write (OUTPUT_UNIT, '(A)') char_fp(i)
  end do
end subroutine

end program
```

Dependencies

- M_CLI2
- ciaaw
- ecx
- ieee_arithmetic
- iso_fortran_env

Procedures

4.1.1 get_help_saw (function)

function get_help_saw() -> res

Get the help text for the subcommand saw.

Returns

res
[character(len=80), allocatable, dimension(:)]

4.1.2 print_text (subroutine)

subroutine print_text(char_fp)

Arguments

char_fp
[character(len=:), pointer, intent(in), dimension(:)]

CHANGELOG

5.1 Version 0.1.0-dev

- Implementation of eis + C API
- Python wrappers for eis.

PYTHON MODULE INDEX

p

[pyecx](#), 14

INDEX

B

`bv (function)`, 7

C

`capi_bv (subroutine)`, 10
`capi_get_version (function)`, 10
`capi_kTe (subroutine)`, 10
`capi_nernst (function)`, 10
`capi_nm2eV (subroutine)`, 10
`capi_sbv (subroutine)`, 10
`capi_z (subroutine)`, 10

E

`ecx (module)`, 7
`ecx__api (module)`, 7
`ecx__capi (module)`, 10
`ecxcli (program)`, 15

G

`get_help_saw (function)`, 15
`get_version (function)`, 7

K

`kTe (function)`, 7

M

`mm (subroutine)`, 7
`module`
 `pyecx`, 14

N

`nernst (function)`, 7

P

`print_text (subroutine)`, 15
`pyecx`
 `module`, 14

S

`sbv (function)`, 7

Z

`z (subroutine)`, 7