
ecx

Release 0.1.0dev0

Milan Skocic

Jan 03, 2026

CONTENTS

1	Getting Started	3
2	Examples	5
3	APIs	7
4	Changelog	15
	Python Module Index	17

Modern Fortran

A purple rounded rectangle containing the white text "ECX".

ECX

Electrochemistry for Fortran.

GETTING STARTED

1.1 Introduction

ecx a Fortran library for providing a collection of routines for electrochemistry. A C API allows usage from C, or can be used as a basis for other wrappers. A Python wrapper allows easy usage from Python.

To use *ecx* within your *fpm* project, add the following lines to your file:

```
[dependencies]
ecx = { git="https://github.com/MilanSkocic/ecx.git" }
```

1.2 Dependencies

```
gcc>=10
gfortran>=10
fpm>=0.7
stdlib>=0.7
```

1.3 Installation

A Makefile is provided, which uses *fpm*, for building the library.

- On windows, *msys2* needs to be installed. Add the *msys2* binary (usually C:\msys64\usr\bin) to the path in order to be able to use *make*.
- On Darwin, the *gcc* toolchain needs to be installed.

```
chmod +x configure.sh
./configure.sh
make
make test
make install
make uninstall
```

You need a compiler that can compile the *stdlib*.

1.4 License

MIT

EXAMPLES

2.1 Fortran

```
program example_in_f
  use iso_fortran_env
  use ecx
  implicit none

  real(real64) :: w(3) = [1.0d0, 1.0d0, 100.0d0]
  real(real64) :: r = 100.0d0
  real(real64) :: p(3) = 0.0d0
  character(len=1) :: e
  integer :: errstat
  complex(real64) :: zout(3)
  character(len=:), pointer :: errmsg

  p(1) = r
  e = "R"
  call z(p, w, zout, e, errstat, errmsg)
  print *, zout
  print *, errstat, errmsg

end program
```

2.2 C

```
#include <stdio.h>
#include <stdlib.h>
#include "ecx.h"

int main(void){

  int errstat, i;
  double w[3] = {1.0, 1.0, 1.0};
  double p[3] = {100.00, 0.0, 0.0};
  ecx_cdouble z[3] = {ecx_cbuild(0.0,0.0),
                      ecx_cbuild(0.0, 0.0),
```

(continues on next page)

(continued from previous page)

```

                                ecx_cbuild(0.0, 0.0));
char *errmsg;

ecx_eis_z(p, w, z, 'R', 3, 3, &errstat, &errmsg);

for(i=0; i<3;i++){
    printf("%f %f \n", creal(z[i]), cimag(z[i]));
}
printf("%d %s\n", errstat, errmsg);
return EXIT_SUCCESS;
}

```

2.3 Python

```

from pyecx import eis
import matplotlib.pyplot as plt

R = 100
C = 1e-6
w = np.logspace(6, -3, 100)

p = np.asarray([R, 0.0, 0.0])
zr = np.asarray(eis.z("R", w, p))
p = np.asarray([C, 0.0, 0.0])
zc = np.asarray(eis.z("C", w, p))
zrc = zr*zc / (zr+zc)
print("finish")

fig = plt.figure()
ax = fig.add_subplot(111)

ax.set_aspect("equal")
ax.plot(zrc.real, zrc.imag, "g.", label="R/C")

ax.invert_yaxis()

plt.show()

```

3.1 Fortran

<https://milanskocic.github.io/ecx/ford/index.html>

3.1.1 Module ecx

Main module for ecx.

3.1.2 Module ecx__api

API Procedures

Function `get_version`

`function get_version() -> fptr`

Get the version.

Returns

fptr

[character(len=:), pointer] Version of the library.

Function `kTe`

`pure elemental function kTe(T) -> r`

Compute the thermal voltage.

Arguments

T

[real(dp), intent(in)] Temperature in °C.

Returns

r

[real(dp)] Thermal voltage in V.

Subroutine `z`

`subroutine z(p, w, zout, e, errstat, errmsg)`

Arguments

p

[real(dp), intent(in), dimension(:)]

w
[real(dp), intent(in), dimension(:)] Angular frequencies in rad.s-1

zout
[complex(dp), intent(out), dimension(:)] Complex impedance in Ohms.

e
[character(len=1), intent(in)] Electrochemical element: R, C, L, Q, O, T, G

errstat
[integer(int32), intent(out)] Error status

errmsg
[character(len=:), intent(out), pointer] Error message

Subroutine mm

subroutine mm(p, w, zout, n)

Arguments

p
[real(dp), intent(in), dimension(:)] Compute the measurement model.

w
[real(dp), intent(in), dimension(:)] Parameters.

zout
[complex(dp), intent(out), dimension(:)] Angular frequencies in rad.s-1

n
[integer(int32), intent(in)] Complex impedance in Ohms.

Function nernst

pure function nernst(E0, z, aox, vox, ared, vred, T) -> E

Compute the Nernst electrochemical potential in V.

Arguments

E0
[real(dp), intent(in)]

z
[integer(int32), intent(in)] Standard electrochemical potential in V.

aox
[real(dp), intent(in), dimension(:)] Number of exchanged electrons.

vox
[real(dp), intent(in), dimension(:)] Activities of the oxidants.

ared
[real(dp), intent(in), dimension(:)] Coefficients for the oxidants.

vred
[real(dp), intent(in), dimension(:)] Activities of the reductants

T
[real(dp), intent(in)] Coefficients for the reductants.

Returns

E
[real(dp)] Temperature in °C.

Function sbv

pure elemental function sbv(U, OCV, j0, aa, ac, za, zc, A, T) -> I

Arguments

U
[real(dp), intent(in)] Open Circuit Voltage in V.

OCV
[real(dp), intent(in)] Compute Butler Volmer equation without mass transport.

j0
[real(dp), intent(in)] Electrochemical potential in V.

aa
[real(dp), intent(in)] Exchange current density in A.cm-2.

ac
[real(dp), intent(in)] Anodic transfer coefficient.

za
[real(dp), intent(in)] Cathodic transfer coefficient.

zc
[real(dp), intent(in)] Number of exchnaged electrons in the anodic branch.

A
[real(dp), intent(in)] Number of exchnaged electrons in the cathodic branch.

T
[real(dp), intent(in)] Area in cm2.

Returns

I
[real(dp)] Temperature in °C.

Function bv

pure elemental function bv(U, OCV, j0, jdla, jdle, aa, ac, za, zc, A, T) -> I
Compute Butler Volmer equation with mass transport.

Arguments

U
[real(dp), intent(in)] Open Circuit Voltage in V.

OCV
[real(dp), intent(in)]

j0
[real(dp), intent(in)] Electrochemical potential in V.

jdla
[real(dp), intent(in)] Exchange current density in A.cm-2.

jdle
[real(dp), intent(in)] Anodic diffusion limiting current density in A.cm-2.

aa
[real(dp), intent(in)] Cathodic diffusion limiting current density in A.cm-2.

ac
[real(dp), intent(in)] Anodic transfer coefficient.

za
[real(dp), intent(in)] Cathodic transfer coefficient.

zc
[real(dp), intent(in)] Number of exchnaged electrons in the anodic branch.

A
[real(dp), intent(in)] Number of exchnaged electrons in the cathodic branch.

T
[real(dp), intent(in)] Area in cm2.

Returns

I
[real(dp)] Temperature in °C.

3.1.3 Module ecx__capi

Procedures

Function capi_get_version

```
function capi_get_version()bind(c, name="ecx_get_version") -> cptr
```

C API - Get the version.

Returns

cptr
[type(c_ptr)]

Subroutine capi_nm2eV

```
pure subroutine capi_nm2eV(lambda, E, n)bind(C, name="ecx_core_nm2eV")
```

Arguments

lambda
[real(c_double), intent(in), dimension(n)] Wavelength in nm.

E
[real(c_double), intent(out), dimension(n)] Energy in eV.

n
[integer(c_size_t), intent(in), value] Size of lambda and E.

Subroutine capi_kTe

```
pure subroutine capi_kTe(T, kTe_, n)bind(C, name="ecx_core_kTe")
```

Arguments

T
[real(c_double), intent(in), dimension(n)] Temperature in °C.

kTe_
[real(c_double), intent(out), dimension(n)] Thermal voltage in V.

n
[integer(c_size_t), intent(in), value] Size of T and kTe.

Subroutine capi_z

subroutine capi_z(p, w, zout, e, k, n, errstat, errmsg)bind(C, name="ecx_eis_z")

Arguments

p
[real(c_double), intent(in), dimension(k)] Parameters.

w
[real(c_double), intent(in), dimension(n)] Angular frequencies in rad.s⁻¹

zout
[complex(c_double_complex), intent(out), dimension(n)] Complex impedance in Ohms.

e
[character(len=1,kind=c_char), intent(in), value] Electrochemical element: R, C, L, Q, O, T, G

k
[integer(c_size_t), intent(in), value] Size of p

n
[integer(c_size_t), intent(in), value] Size of w

errstat
[integer(c_int), intent(out)] Error status

errmsg
[type(c_ptr), intent(out)] errmsg Error message

Function capi_nernst

pure function capi_nernst(E0, z, aox, vox, nox, ared, vred, nred, T)bind(C, name="ecx_kinetics_nernst") -> E

Compute the Nernst electrochemical potential in V.

Arguments

E0
[real(c_double), intent(in), value]

z
[integer(c_int), intent(in), value] Standard electrochemical potential in V.

aox
[real(c_double), intent(in), dimension(nox)] Number of reductants.

vox
[real(c_double), intent(in), dimension(nox)] Activities of the oxidants.

nox
[integer(c_size_t), intent(in), value] Number of exchanged electrons.

ared
[real(c_double), intent(in), dimension(nred)] Coefficients for the oxidants.

vred

[real(c_double), intent(in), dimension(nred)] Activities of the reductants

nred

[integer(c_size_t), intent(in), value] Number of oxidants.

T

[real(c_double), intent(in), value] Coefficients for the reductants.

Returns**E**

[real(c_double)] Temperature in °C.

Subroutine capi_sbv

```
pure subroutine capi_sbv(U, OCV, j0, aa, ac, za, zc, A, T, I, n)bind(c,  
name="ecx_kinetics_sbv")
```

Compute Butler Volmer equation without mass transport.

Arguments**U**

[real(c_double), intent(in), dimension(n)] Open circuit potential in volts.

OCV

[real(c_double), intent(in), value] Size of U and I.

j0

[real(c_double), intent(in), value] Potential in volts.

aa

[real(c_double), intent(in), value] Exchange current density in A.cm-2.

ac

[real(c_double), intent(in), value] Anodic transfert coefficient.

za

[real(c_double), intent(in), value] Cathodic transfert coefficient.

zc

[real(c_double), intent(in), value] Number of exchanged electrons in anodic branch.

A

[real(c_double), intent(in), value] Number of exchanged electrons in cathodic branch.

T

[real(c_double), intent(in), value] Area in cm2.

I

[real(c_double), intent(out), dimension(n)] Temperature in °C.

n

[integer(c_size_t), intent(in), value]

Subroutine capi_bv

```
pure subroutine capi_bv(U, OCV, j0, jdla, jdle, aa, ac, za, zc, A, T, I, n)bind(c,  
name="ecx_kinetics_bv")
```

Compute Butler Volmer equation without mass transport.

Arguments

U
[real(c_double), intent(in), dimension(n)] Open circuit potential in volts.

OCV
[real(c_double), intent(in), value] Size of U and I.

j0
[real(c_double), intent(in), value] Potential in volts.

jdl
[real(c_double), intent(in), value] Exchange current density in A.cm-2

jdlc
[real(c_double), intent(in), value] Anodic diffusion limiting current density in A.cm-2.

aa
[real(c_double), intent(in), value] Cathodic diffusion limiting current density in A.cm-2.

ac
[real(c_double), intent(in), value] Anodic transfert coefficient.

za
[real(c_double), intent(in), value] Cathodic transfert coefficient.

zc
[real(c_double), intent(in), value] Number of exchanged electrons in anodic branch.

A
[real(c_double), intent(in), value] Number of exchanged electrons in cathodic branch.

T
[real(c_double), intent(in), value] Area in cm2.

I
[real(c_double), intent(out), dimension(n)] Temperature in °C.

n
[integer(c_size_t), intent(in), value]

3.2 C

```
#ifndef ECX_H
#define ECX_H
#include <complex.h>
#if _MSC_VER
    #define ADD_IMPORT __declspec(dllimport)
    typedef _Dcomplex ecx_cdouble;
    #define ecx_cbuild(real, imag) (_Cbuild(real, imag))
#else
    #define ADD_IMPORT
    typedef double _Complex ecx_cdouble;
    #define ecx_cbuild(real, imag) (real+I*imag)
#endif

extern char* ecx_get_version(void);

ADD_IMPORT extern const double ecx_core_PI;
```

(continues on next page)

(continued from previous page)

```
ADD_IMPORT extern const double ecx_core_T_K;
void ecx_core_nm2eV(double *lambda, double *E, size_t n);
void ecx_core_kTe(double *U, double *kTE, size_t n);

extern double ecx_kinetics_nernst(double E0, int z,
                                   double *aox, double *vox, size_t nox,
                                   double *ared, double *vred, size_t nred,
                                   double T);

extern void ecx_kinetics_sbv(double *U, double OCV, double j0,
                             double aa, double ac, double za, double zc,
                             double A, double T, double *i, size_t n);

extern void ecx_kinetics_bv(double *U, double OCV, double j0, double jdla, double jdla,
                             double aa, double ac, double za, double zc,
                             double A, double T, double *i, size_t n);

extern void ecx_eis_z(double *p, double *w, ecx_cdouble *z,
                      char e, size_t k, size_t n,
                      int *errstat, char *(*errmsg));

#endif
```

3.3 Python

Python wrapper of the (Modern Fortran) ecx library.

CHANGELOG

4.1 Version 0.1.0-dev

- Implementation of eis + C API
- Python wrappers for eis.

PYTHON MODULE INDEX

p

[pyecx](#), 14

INDEX

B

`bv (function)`, 7

C

`capi_bv (subroutine)`, 10

`capi_get_version (function)`, 10

`capi_kTe (subroutine)`, 10

`capi_nernst (function)`, 10

`capi_nm2eV (subroutine)`, 10

`capi_sbv (subroutine)`, 10

`capi_z (subroutine)`, 10

E

`ecx (module)`, 7

`ecx__api (module)`, 7

`ecx__capi (module)`, 10

G

`get_version (function)`, 7

K

`kTe (function)`, 7

M

`mm (subroutine)`, 7

module

`pyecx`, 14

N

`nernst (function)`, 7

P

`pyecx`

 module, 14

S

`sbv (function)`, 7

Z

`z (subroutine)`, 7